# **RAW-based Workflow:**

Memory Card

## Unsorted RAW Images --> FastRawViewer --> Adobe Lr/ACR or other RAW Converter



http://www.fastrawviewer.com website: support@fastrawviewer.com email:

open the folder to be sorted in FastRawViewer

Drag-and-drop the folder on FRV icon or into the FRV window

(for more options see File menu)

### **FastRawViewer**

### Initial Culling [1], [2]

Choose "keepers" and copy them to the designated folder or folders on a hard drive copy chosen images oneby-one to a designated folder on a hard drive

> C - new folder Shift-C - same folder

"Keepers" Folder on the Hard Drive

open the folder with the "keepers" File --> Recent Folders --> top positions in the drop-down list

continue to work with the Original Folder in FastRawViewer

files from the Rejected subfolder won't be opened

**FastRawViewer** 

#### Initial Adjustments [3]

- 1. Orientation
- 2. Exposure (brightness)
- 3. White Balance
- 4. Contrast (Tone) Curve
- 5. Shadow Boost

#### **Assigning Labels** and Ratings

User adjustments are recorded as XMP sidecar files in the current folder with images

run external program directly from FastRawViewer

R (Alt-R, Ctrl-R)

if using \_Rejected subfolder, make sure to uncheck "Include Subfolders" box in Adobe Lr "From" field

External Program [4] (Adobe Lr/ACR, other RAW converter, RawDigger, etc.)

Catalogue Converting **Editing** Researching etc.

The Source Folder on a Hard Drive

open the source folder in FastRawViewer

> Command-Shift-O (for more options

> > see File menu)

and move them into \_Rejected Subfolder of the Source Folder

**FastRawViewer** 

move every rejected Initial Culling [1] image to the \_Rejected Subfolder Cull rejected images

> move current image Alt-Shift-Delete

move previous image Shift-Command-[

on the Hard Drive Rejected SubFolder of the Source Folder)

The Source Folder

later you can recheck rejected files in order to make sure that you really don't want to keep them

restore from Rejected Shift-Command-]



Check rejected images and if necessary move them from the \_Rejected sublfolder back to the Original Folder or to the \_Rejected subfolder of the \_Rejected subfolder

**FastRawViewer** 

### **FRV Technical Tools for Culling** based on RAW data:

- 1. RAW Histogram
- 2. OE-, UE indication
- 3. Per-channel View
- 4. Focus Peaking

For a quick start, please look at the "Tips" pop-up at every launch of FRV; for detailed instructions, please read the manual.

[2]

#### Copy or Move?

Instead of copying "keepers" you can move them to the designated folder:

M - new folder

**Shift-M** - same folder as previous

#### Initial Adjustments to an Image **Assigning Ratings and Labels**

For a quick start, please look at the "Tips" pop-up at every launch of FRV; for detailed instructions, please read the manual.

**Integration with External Programs** 

Please look at the "Tips" and read the manual to get detailed instructions how to:

- 1. add an external program to FRV;
- 2. launch an external program;
- 3. adjust settings to save changes in XMP sidecar files;
- 4. match an image display.

